


# Changer le port RDP par défaut

On se rend dans regedit (Win + r, regedit) puis on se rend dans  
HKEY\_LOCAL\_MACHINE\SYSTEM\CurrentControlSet\Control\Terminal Server\WinStations\RDP-Tcp  
On modifie l'entrée "PortNumber".



Ordinateur\HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Terminal Server\WinStations\RDP-Tcp			
	Nom	Type	Données
	MinEncryptionL...	REG_DWORD	0x00000002 (2)
	NWLogonServer	REG_SZ	
	OutBufCount	REG_DWORD	0x00000006 (6)
	OutBufDelay	REG_DWORD	0x00000064 (100)
	OutBufLength	REG_DWORD	0x00000212 (530)
	Password	REG_SZ	
	PdClass	REG_DWORD	0x00000002 (2)
	PdClass1	REG_DWORD	0x0000000b (11)
	PdDLL	REG_SZ	tdtcp
	PdDLL1	REG_SZ	tssecsrv
	PdFlag	REG_DWORD	0x0000004e (78)
	PdFlag1	REG_DWORD	0x00000000 (0)
	PdName	REG_SZ	tcp
	PdName1	REG_SZ	tssecsrv
	PortNumber	REG_DWORD	0x00000d3e (3390)
	SecurityLayer	REG_DWORD	0x00000002 (2)
	SelectNetworkD...	REG_DWORD	0x00000001 (1)
	SelectTransport	REG_DWORD	0x00000002 (2)
	Shadow	REG_DWORD	0x00000001 (1)
	UserAuthenticat...	REG_DWORD	0x00000001 (1)
	Username	REG_SZ	
	WdFlag	REG_DWORD	0x00000036 (54)
	WdName	REG_SZ	Microsoft RDP 8.0
	WdPrefix	REG_SZ	RDP

On ajoute ensuite une règle dans le pare-feu pour autoriser le trafic entrant.

Revision #5

Created 25 January 2021 18:19:06 by Khroners

Updated 30 December 2021 01:52:44 by Khroners